

Seacrest WiFi Printing on Windows 8 or 8.1

Windows 8:

Open your Charms Bar.

Click on the Search icon.

Type Devices and Printers.

Click on the Settings button.

Click on the Devices and Printers icon.

Once the new window opens, click on Add a Printer.

Click The printer I want is not listed.

Click the bubble for Add a printer using a TCP/IP address or hostname, then type in the IP address labeled on the printer of your choice.

On the Install the printer driver page, select HP as the manufacturer, and HP Laserjet 4200/4300 driver for the HP 4240, or the appropriately named series of driver for the printer to which you're attempting to connect. If you do not see it, click on the Windows Update button and allow windows to update all known printer drivers on your computer. This will take some time so please use patience. Double click the driver and the screen will change.

In the Printer Name: field, rename the printer to whatever you'd like or keep it the same.

Click Next.

Click on the bubble for Do not share this printer, then click Next.

Only check the box for Set as the default printer if you want this to be your default printer. If you do so accidentally, simply right click the icon for the printer you want to be the default option and select Set as default printer.

Click Finish.

Windows 8.1

Go to the Start Screen.

Type (anywhere) Devices and Printers; this will queue Windows Search and find the Devices and Printers Settings page.

Click on Add a printer, then click The printer that I want isn't listed.

Click Next.

Click the bubble for 'Add a printer using a TCP/IP address or hostname'.

Click Next.

Select the Hostname or IP address field and type in the IP address on the label of the printer you want to connect.

If the computer does not automatically find the correct printer driver perform these operations:

- On the Install the printer driver page, select HP as the manufacturer, and HP Laserjet 4200/4300 driver for the HP 4240, or the appropriately named series of driver for the printer to which you're attempting to connect. If you do not see it, click on the Windows Update button and allow windows to update all known printer drivers on your computer. This will take some time so please use patience. Double click the driver and the screen will change.

In the Printer Name: field, rename the printer to whatever you'd like or keep it the same.

Click Next.

Click on the bubble for Do not share this printer, then click Next.

Only check the box for Set as the default printer if you want this to be your default printer. If you do so accidentally, simply right click the icon for the printer you want to be the default option and select Set as default printer.

Click Finish.